

Network Job Flow Display

The Network Job Flow Display option provides a short overview of the job flow within a network. The output can be sent to the screen or printed.

To invoke the Network Job Flow Display

1. Type its option number in the Option field on the Reporting Menu. Press Enter.

A window opens in which you can enter the owner and the network for which to display information:

| | | |
|--|--|----------|
| 06.11.01 | *** Entire Operations 4.1.1 *** | 18:48:35 |
| Owner UKSJU | +-----+ ----- ! ! | |
| | ! Network Job Flow Display ! | |
| Reportin | ! ! | |
| | ! Owner.....: UKSJU_____ (Blank for all, * for selection ! | |
| 1 Log - Te | ! Network....: _____ or * and PF4 to process all ! | |
| 2 Log - Ab | ! matching objects) ! | |
| 3 Log - Jo | ! ! | |
| 4 Accounti | ! ! | |
| 5 Network | ! Destination: 1 ! | |
| 6 Network | ! 1 - Screen 2 - Printer 3 - PC 4 - PC-CSV ! | |
| 7 Network | ! ! | |
| 8 Network | ! Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9--- ! | |
| 9 Schedule | ! Help End Apply Acpt ! | |
| 10 Network | +-----+ ----- ! | |
| 11 Network | Schedule Overview | |
| 12 Activation | Overview | |
| Command => 8_____ | | |
| Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12--- Help End Old Menu | | |

Note:

Job is not a selection criterion.

The selection fields are preset with '*'. This causes an object selection to be displayed after Enter is displayed. If all objects are to be selected, the corresponding selection field must be deleted.

The contents of the output fields result in the following:

| Owner | Network | Selection |
|--------|---------|--|
| empty | empty | All owners und networks are displayed. |
| filled | empty | All networks for the selected owner are displayed. |
| filled | * | Network selection for the selected owner is invoked. |

Network selection is only executed, if an owner has already been selected.

2. Enter the Owner and Network in the selection window. Press Enter.

A window opens at the bottom of the screen in which you are asked Send Output to Printer?

3. If you enter **Y** and press Enter, output is printed on printer assigned to Workfile 1.
If you enter **N** and press Enter, the Job Flow screen appears, for example:

| MORE | | Entire Operations 4.1.1 | | | 17:16:44 |
|----------|--------------|------------------------------|--------|---------|----------|
| 02.11.01 | | Job Flow of Network E60-FLOW | | | Page 1 |
| | | Owner EXAMPLE | | | |
| Job | by Condition | from/to Job | Owner | Network | |
| ----- | | | | | |
| (1) | JOB-01 | | | | |
| | I | E60-JOB1-O | | | |
| | +-----> | E60-JOB1-O | -----> | (11) | JOB-019 |
| (2) | JOB-012 | | | | |
| | I | E60-J012-O | | | |
| (3) | JOB-013 | | | | |
| | I | E60-J013-O | | | |
| (4) | JOB-014 | | | | |
| | I | E60-J014-O | | | |
| (5) | JOB-015 | | | | |
| | I | E60-J015-O | | | |
| | +<----- | E60-J019-O | <----- | (11) | JOB-019 |
| (6) | JOB-02 | | | | |
| | I | E60-JOB2-O1 | | | |
| (7) | JOB-03 | | | | |

Notes on the above list:

- Each job is identified by a sequence number.
 - Direct successor jobs appear in vertical order.
 - If the direct sequence is interrupted, a horizontal line is printed.
 - If a successor cannot be shown indirectly, an arrow --> points from the left.
 - If a predecessor cannot be shown directly, an arrow <-- points from the right.
 - The linking conditions are shown on the right-hand side of the screen.
 - Input conditions dependent on files and dependent on job variables (BS2000) are displayed.
4. Press Enter to display the next screen, if there is more data.
 5. Press PF3 (End) to return to the Reporting Menu.

